



Installation & Configuration Guide

Environmental Noise Cancellation Software

Version 1.0.0

Release Date: 01/07/2026

SAN Softwares Pvt. Ltd.

419, 4th Floor, M3M Urbana, Sector 67, Gurgaon, Haryana, India - 122018
sales@sansoftwares.com | support@sansoftwares.com

Table of Contents

Table of Contents.....	2
1. Overview.....	3
1.1 How It Works.....	3
2. System Requirements.....	4
3. Licensing.....	4
4. Installation Steps.....	4
5. Configuration.....	8
5.1 Accessing Settings.....	8
5.2 Settings Screen.....	9
5.3 Microphone Selection.....	9
5.4 Virtual Audio Cable.....	9
5.5 Performance Mode.....	10
6. Technical Support.....	10

1. Overview

SanClarity is an Environmental Noise Cancellation application developed by SAN Softwares. It runs in the background and filters ambient/environmental noise from your microphone input in real time, before the audio reaches any communication application.

SanClarity acts as a smart layer between agent and customer communication for online audio and video calls, and works seamlessly with any application that uses a microphone, including but not limited to:

- SanCCS
- Google Meet
- Microsoft Teams
- Zoom Meeting
- ZOHO
- Zendesk
- SanIPPBX
- AI Voice Agent
- Any other Call Center Solution, Soft Phone, or application that accepts a microphone/audio input

Noise Cancellations Works with All Platforms

Smart layer between agent & customer communication for online audio and video calls:



Figure 1: SanClarity — Works with All Platforms

Once installed, SanClarity runs as a background application and appears as an icon in the Windows taskbar (system tray). All configuration is done through this tray icon.

1.1 How It Works

SanClarity intercepts audio from your selected physical microphone, filters out environmental noise using its built-in noise cancellation engine, and routes the clean, filtered audio through a Virtual Audio Cable. Any application that needs a microphone should then use this Virtual Audio Cable as its input device.




Figure 2: SanClarity Architecture — Signal Flow

2. System Requirements

Requirement	Details
Processor	Intel Core i3 or above (or equivalent)
RAM	8 GB or above
Operating System	Windows (with Virtual Audio Cable support)
Software Version	1.0.0
Release Date	01/07/2026

3. Licensing

SanClarity licenses are provided on a SaaS (Software as a Service) subscription basis.

- Once the client confirms the required number of licenses, SAN Softwares will activate the license(s) accordingly.
- Until a license key is applied, SanClarity runs in trial mode for 30 days with full functionality.
- License activation and management can be done from the Settings screen after entering the admin password.

4. Installation Steps

Follow the steps below to install SanClarity on your system. Ensure your system meets the requirements listed in Section 2 before proceeding.

Step 1: Download SanClarity

Visit the download page and choose the version that matches your role: the Admin Panel (for supervisors, to manage agents, monitor calls, and configure system settings) or the Agent App (for agents, to handle customer calls with AI-powered noise cancellation tools).




Figure 3: Choose and download the version that matches your role

Step 2: Extract the Downloaded Files

The download will be a compressed (zipped) folder. Right-click the SanClarity.zip file, select “Extract All...”, choose a destination folder, and click “Extract”.





Figure 4: Extract the downloaded ZIP folder

Step 3: Grant Permission to Run the Installer

Open the extracted folder and run setup.exe. Windows may show a SmartScreen protection prompt since the app is newly published. Click “Run anyway” to proceed with the installation.

*Figure 5: Grant permission — “Run anyway”*

Step 4: Start the Setup Wizard

The SanClarity Setup Wizard will open with a welcome screen. Click “Next” to continue.





Figure 6: Setup Wizard — Welcome screen


Step 5: Select Installation Folder

Keep the default installation folder or click “Browse” to choose a different one. Select whether to install SanClarity for “Everyone” on this computer or “Just me”, then click “Next”.

*Figure 7: Select installation folder and install scope*

Step 6: Confirm Installation

Review the confirmation screen and click “Next” to begin installing SanClarity on your computer.

*Figure 8: Confirm installation*

Step 7: Complete Installation

Once installation finishes, you will see the “Installation Complete” screen. Click “Close” to exit the setup wizard. If prompted, use Windows Update to check for any critical .NET Framework updates.




Figure 9: Installation complete

5. Configuration

After installation, SanClarity runs in the background and appears as an icon in the Windows taskbar (system tray).




Figure 10: SanClarity icon in the taskbar — right-click menu

5.1 Accessing Settings

Right-click the SanClarity icon in the taskbar and select “Settings.” You will be prompted to enter a password.




Figure 11: Password prompt

Default password: **admin**

5.2 Settings Screen

The Settings screen allows you to configure the following:

- License Details — view trial status or activate your license key
- Microphone — select your physical microphone device
- Virtual Audio Cable — verify the output routing device
- Performance Mode — choose the noise cancellation quality level

Figure 12: SanClarity Settings screen

5.3 Microphone Selection

In the Microphone dropdown, select the physical microphone device you want SanClarity to capture audio from.

5.4 Virtual Audio Cable

The Virtual Audio Cable field should always show “Virtual Audio Cable.” If it does not appear, the software has not been installed correctly and the installation should be repeated.

In every application where you want to use a microphone (Call Center Solution, Soft Phone, Google Meet, Teams, etc.), select “Virtual Audio Cable” as the microphone/input device. SanClarity performs noise filtration behind this virtual device.

5.5 Performance Mode

SanClarity offers 5 Performance Mode options, ranging from Low to Maximum. Select the option that best matches your noise cancellation quality requirement — higher modes provide stronger filtration but may use more system resources.

6. Technical Support

For any installation or configuration assistance, please reach out to our support team:

Contact	Details
Support Email	support@sansoftwares.com
Sales Email	sales@sansoftwares.com
Phone	+91 98100 18735 / +91-124-4310735
Address	419, 4th Floor, M3M Urbana, Sector 67, Gurgaon, Haryana, India - 122018